
# Setting Up Your E-mail in Microsoft Outlook


This tutorial shows you how to set up Microsoft Outlook to work with your e-mail account. This tutorial focuses on setting up Microsoft Outlook 2003, but these settings are similar in other versions of Microsoft Outlook. You can set up previous versions of Microsoft Outlook by using the settings in this tutorial.

# To Set Up Your E-mail Account in Microsoft Outlook

1. In Microsoft Outlook, select Tools > E-mail Accounts.



2. On the E-mail Accounts wizard window, select "Add a new e-mail account" and click Next.



3. For your server type, select "POP3" and click Next.

E-mail Accounts	
Server Type You can choose the type of server your new e-mail account will work with.	×
O Microsoft Exchange Server	
Connect to an Exchange server to read e-mail, access public folders, and share documents.	
Connect to a POP3 e-mail server to download your e-mail.	
Connect to an IMAP e-mail server to download e-mail and synchronize mailbox folders.	
<u>О н</u> ттр	
Connect to an HTTP e-mail server such as Hotmail to download e-mail and synchronize mailbox folders.	
<u>A</u> dditional Server Types	
Connect to another workgroup or 3rd-party mail server.	
< <u>B</u> ack Next >	Cancel

4. On the Internet E-mail Settings (POP3) window, enter your information as follows:

## Your Name

Enter your first and last name.

## E-mail Address

Enter your e-mail address.

#### **User Name**

Enter your e-mail address, again.

# Password

Enter the password you set up for your e-mail account.

### Incoming mail server (POP3)

Enter mail.almanargroup.com for your incoming mail server.


### Outgoing mail server (SMTP)

Enter mail.almanargroup.com for your outgoing mail server.

User Informat	tion	Server Information	
Your Name:	Samy Fawzy al-Qasim	Incoming mail server (POP3):	mail.almanargroup.com
<u>E</u> -mail Address:	samy@almanargroup.com	Outgoing mail server (SMTP):	mail.almanargroup.com
Password:	Remember password	recommend you test your acco button below. (Requires netwo Test Account Settings	
	Secure Password on (SPA)		

Click "More Settings."

- 5. On the Internet E-mail Settings window, select the "Outgoing Server" tab.
- 6. Select "My outgoing server (SMTP) requires authentication."



- 7. Select the "Advanced" tab and change the "Outgoing server (SMTP)" port to **26.**
- 8. Click OK.

nternet	E-mail Settings				X		
General	Outgoing Server	Connection	Advanced				
	Port Numbers	110	Use	Defaults			
	This server requir		ted connection	on (SSL)			
	oing server (SMTP):	L. Constanting	ted connection	on (SSL)			
	Timeouts	Long 1	minute				
Deliver	y						
	ave a copy of mess	ver after 10	days				
-	Remove from server	ver when dele	sted from 'De	leted Items			
			0		$\geq$		
			ОК	Cance	el		

For the outgoing server (SMTP): please write 587

If you have windows hosting, please click outgoing server and check the box My outgoing server requires Authentication.

# 9. Click Next.

E-mail Account	5						
	ail Settings (POP3) ese settings are required to g	et your e-mail account working.	茶				
User Informat	tion	Server Information	5				
Your Name:	Samy Fawzy al-Qasim	Incoming mail server (POP3):	mail.almanargroup.com				
E-mail Address:	samy@almanargroup.com	Outgoing mail server (SMTP):	mail.almanargroup.com				
Logon Information		Test Settings					
<u>U</u> ser Name:	samy@almanargroup.com	After filling out the information on this screen, we recommend you test your account by clicking the					
Password:	*****	button below. (Requires netwo					
	Remember password	Test Account Settings					
Log on using Authenticatio	Secure Password on (SPA)		More Settings				
	VX	< Back	Next > Cancel				

# 10. Click Finish.

